

## Dispatch Confirmation

A new job class has been added called 'Dispatching'. When this job class is active Dispatching jobs will be automatically created when a shipment reaches the Trailing Status of "Awaiting Dispatch Confirmation."

Users will be able to set up Dispatching Profiles. In the profile users will be able to:

- Enter Profile Name
- Enable or disable the "Required Electronic Signature" checkbox
- Enable or disable the "Required Print Name" checkbox

[Dispatching Profile List](#) > [Edit Dispatching Profile \(New Dispatching Profile\)](#)

General

General

Name

New Dispatching Profile

☒ Require Electronic Signature


☒ Require Print Name

When a shipment has reached the trailing status of 'Awaiting Dispatch Confirmation', then users will be able to execute the dispatch job via the Dispatch Job Execution by selecting a profile and entering a load number.

If the load number matches, then the user will be asked for an electronic signature

and/or print name if enabled on the selected profile.

## Dispatching Job Execution




The screenshot shows a web form for dispatching job execution. It includes a 'Profile' dropdown menu with 'New Dispatching Profile' selected. Below it is a 'Load Number' field with 'LD-DCC##27' entered. A 'Signature' section contains a handwritten signature 'AT' and a 'Clear Signature' button. At the bottom is a 'Print Name' field with 'AARON THOMAS' entered.

Once the user has successfully confirmed the required information the shipment will be updated to have both leading and trailing status of 'Closed'.

The user will still be able to close a Load with a Trailing Status of "Awaiting Dispatch Confirmation" through the Shipping Enquiry > Shipment tab. Once the user confirms the closure, the corresponding Dispatch job will be removed.

In the loading profile, a new checkbox has been added for 'Trailer Number Required' and a new tab called 'Continue to Dispatching'. When a loading job has been completed it will continue to dispatching execution using the outlined profile if enabled.



The screenshot shows a web form for the 'Loading Profile List'. It has a breadcrumb trail 'Loading Profile List > Edit Staging Profile (Loading Pending)'. There are two tabs: 'General' (active) and 'Continue To Dispatching'. The 'General' tab contains a 'Name' field with 'Loading Pending' and a checkbox labeled 'Trailer Number Required' which is checked.

General **Continue To Dispatching**

**Continue To Dispatching**

☒ Continue To Dispatching

Dispatching Profile  
**New Dispatching Profile**

Please reach out if you wish to know more about this feature.